Book sleeve with a flap

US terms



Finished size
About 9½ in (24 cm) wide and 6¾ in (17 cm) tall when closed

Skill
Beginner
It is one flat piece folded and sewn.

Yarn
Medium (4), 3 colors

Hook
5 mm (US H-8)

Gauge
15 stitches and 17 rows to 4 in (10 cm)
In single crochet.

You will need

Yarn A: heather green, main color	**about 125 yd (114 m), an estimate**
Yarn B: cream, contrast color	**about 25 yd (23 m), an estimate**
Yarn C: chestnut, contrast color	**about 45 yd (41 m), an estimate**

Fiber: cotton

Hook: 5 mm (US H-8). Also: a yarn needle, scissors and a button about ¾ in (2 cm) across, with sewing thread and a sewing needle.

To find how many balls: divide by the length on your yarn's label and round up. The estimate is from the stitches of this size at this gauge, with 30 percent added.

Abbreviations

Written in US terms. Where the UK name differs it is given beside the US one.

ch	chain stitch
sc	single crochet (UK dc, double crochet)
st	stitch
sp	space
sk	skip (UK miss)
RS	right side

For your own crochet, gifts and handmade pieces you sell. Do not resell or share this PDF.

Gauge

15 stitches and 17 rows to 4 in (10 cm) in single crochet. Along a row, count every stitch and every chain between stitches as one.

There should be 15 stitches and 17 rows. If you count more stitches than that, change to a larger hook; if you count fewer, change to a smaller hook. The swatch can be pulled out and its yarn used again.

> **The swatch.** A test piece to measure and pull out. It is not the start of the pattern. Work a swatch before you begin: ch 23; row 1, sc in 2nd ch from hook and in each ch across (22 sc); rows 2 to 26, ch 1, turn, sc in each st across (22 sc). Lay it flat and count the stitches and rows over 4 in (10 cm) in its middle.
>
Swatch foundation	Ch 23.	
Swatch row 1 (RS)	Sc in 2nd ch from hook and in each ch across	**(22 sc)**
Swatch rows 2 to 26	Ch 1, turn; sc in each st across	**(22 sc)**

Before you start

- The chain of 1 at the start of a row does not count as a stitch.
- Whip stitch: put the needle through both edges from back to front, one stitch for each stitch or row, and draw the yarn snug.
- To change color, draw the new yarn through as the last yarn over of the stitch before. Cut the old yarn, leaving a tail of 6 in (15 cm). Where four rows or fewer are worked before the old yarn is used again, do not cut it: carry it loosely up the side.
- Colors, row by row. Rows 1 to 17: A. Rows 18 to 19: B. Rows 20 to 21: A. Rows 22 to 23: B. Rows 24 to 33: A. Rows 34 to 35: B. Rows 36 to 37: A. Rows 38 to 39: B. Rows 40 to 55: A. Rows 56 to 71: C.

Instructions

The count in round brackets at the end of a line is what that line leaves. Tick the box when a row is done. In UK terms sc is double crochet and sk is miss.

Yarns in order of use: A, heather green; B, cream; C, chestnut.

☐	**Foundation**	Ch 37.	
☐	**Row 1 (RS)**	Sc in 2nd ch from hook and in each ch across	**(36 sc)**
☐	**Rows 2 to 17**	Ch 1, turn; sc in each st across	**(36 sc)**

A box for each row, 2 to 17: tick them off as you go.

☐ 2 ☐ 3 ☐ 4 ☐ 5 ☐ 6 ☐ 7 ☐ 8 ☐ 9 ☐ 10 ☐ 11 ☐ 12 ☐ 13 ☐ 14 ☐ 15 ☐ 16 ☐ 17

☐	**Row 18**	With B, ch 1, turn; sc in each st across	**(36 sc)**
☐	**Row 19**	Ch 1, turn; sc in each st across	**(36 sc)**
☐	**Row 20**	With A, ch 1, turn; sc in each st across	**(36 sc)**
☐	**Row 21**	Ch 1, turn; sc in each st across	**(36 sc)**
☐	**Row 22**	With B, ch 1, turn; sc in each st across	**(36 sc)**
☐	**Row 23**	Ch 1, turn; sc in each st across	**(36 sc)**

For your own crochet, gifts and handmade pieces you sell. Do not resell or share this PDF.

☐	**Row 24**	With A, ch 1, turn; sc in each st across	**(36 sc)**
☐	**Rows 25 to 33**	Ch 1, turn; sc in each st across	**(36 sc)**

A box for each row, 25 to 33: tick them off as you go.

25 26 27 28 29 30 31 32 33

☐	**Row 34**	With B, ch 1, turn; sc in each st across	**(36 sc)**
☐	**Row 35**	Ch 1, turn; sc in each st across	**(36 sc)**
☐	**Row 36**	With A, ch 1, turn; sc in each st across	**(36 sc)**
☐	**Row 37**	Ch 1, turn; sc in each st across	**(36 sc)**
☐	**Row 38**	With B, ch 1, turn; sc in each st across	**(36 sc)**
☐	**Row 39**	Ch 1, turn; sc in each st across	**(36 sc)**
☐	**Row 40**	With A, ch 1, turn; sc in each st across	**(36 sc)**
☐	**Rows 41 to 55**	Ch 1, turn; sc in each st across	**(36 sc)**

A box for each row, 41 to 55: tick them off as you go.

41 42 43 44 45 46 47 48 49 50 51 52 53 54 55

☐	**Row 56**	With C, ch 1, turn; sc in each st across	**(36 sc)**
☐	**Rows 57 to 68**	Ch 1, turn; sc in each st across	**(36 sc)**

A box for each row, 57 to 68: tick them off as you go.

57 58 59 60 61 62 63 64 65 66 67 68

☐	**Row 69**	Ch 1, turn; sc in next 16 sts, ch 4, sk next 4 sts, sc in next 16 sts	**(32 sc, 1 ch-4 sp)**
☐	**Row 70**	Ch 1, turn; sc in next 16 sts, 4 sc in next ch-4 sp, sc in next 16 sts	**(36 sc)**
☐	**Row 71**	Ch 1, turn; sc in each st across	**(36 sc)**
☐	**End**	Fasten off, leaving a tail of 6 in (15 cm).	

Assembly

1. Lay the panel right side down with the foundation chain toward you. Fold the first 28 rows up over the next 29, so that the fold lies between rows 28 and 29.

2. For each side cut a length of A about 28 in (71 cm) long. Beginning at the fold with a tail of 6 in (15 cm), whip stitch the two layers together up that side to the foundation chain, row to row (28 rows a side).

3. The last 14 rows are the flap: fold it down over the front. Sew the button to the front under the buttonhole with sewing thread.

Finishing

- Weave every tail in on the wrong side.

In all: 71 rows; 2,552 stitches; 20 ends to weave in.

Found a mistake in this pattern? Tell us at flossfield.com, under Make a request.

For your own crochet, gifts and handmade pieces you sell. Do not resell or share this PDF.