Men's striped ribbed beanie

Man, head 23 in (58 cm) · US terms



Finished size

About 20¾ in (53 cm) round and about 10 in (25 cm) deep with a brim of about 2 in (5 cm) turned up (about 12 in (30 cm) long before it is turned up)

To fit a head of 23 in (58 cm)

Skill

Easy

Half double crochet in rows, color changes, one seam

Yarn

Medium (4), 2 colors

Hook

5.5 mm (US I-9)

Gauge

13 stitches and 10 rounds to 4 in (10 cm)

In half double crochet in back loops, worked in rows.

You will need

Yarn A: pine, the first stripe	**about 130 yd (119 m), an estimate**
Yarn B: ecru, the second stripe	**about 135 yd (123 m), an estimate**

Hook: 5.5 mm (US I-9). Also: a soft tape measure, a yarn needle and scissors.

To find how many balls: divide by the length on your yarn's label and round up. The estimate is from the stitches and chains of this size at this gauge, with 30 percent added.

Sizes

Size	Head	Finished size, about	Yarn, an estimate
Child	19½ in (50 cm)	17½ in (44 cm) round, 8½ in (22 cm) deep	about 195 yd (178 m)
Teen	21 in (53 cm)	19¼ in (49 cm) round, 9 in (23 cm) deep	about 225 yd (206 m)
Man (this file)	**23 in (58 cm)**	**20¾ in (53 cm) round, 10 in (25 cm) deep**	**about 265 yd (242 m)**

For your own crochet, gifts and handmade pieces you sell. Do not resell or share this PDF.

Abbreviations

Written in US terms. Where the UK name differs it is given beside the US one.

ch	chain
sc	single crochet (UK dc, double crochet)
hdc	half double crochet (UK htr, half treble)
BLO	back loop only
st	stitch
RS	right side

Gauge

13 stitches and 10 rounds to 4 in (10 cm) in half double crochet in back loops, worked in rows.

The gauge is measured on the panel itself, laid flat and not stretched, after the tenth row: along a row, which checks the stitches, and then across the rows, in the place that line names, which sets the size round. Below, "round" is measured across the rows in the same way, not stretched.

Check your gauge on the piece. Begin the pattern and measure the piece itself as you go. After row 10, lay the panel flat without stretching it and measure it along a row: it should be about 12 in (30 cm) long.

Before you start

- Measure the head if you can: put a soft tape round its widest part, across the middle of the forehead and just above the ears, and choose the size whose head measurement is nearest. The ribs stretch, so each size is made smaller round than the head it is for, measured flat and not stretched. The list below gives both measures of each size.
- The pattern is written in United States terms; the United Kingdom term stands beside each stitch in the list of abbreviations.
- The chain at the start of a row does not count as a stitch. After the turn the first stitch of the row goes into the stitch nearest the hook, which is the last stitch of the row before, and the last goes into the first stitch of the row before, so that every row has the same number of stitches; the chains skipped at the start of row 1 do not count either.
- Back loop only: of the two loops at the top of a stitch work under the one that lies farther from you as you work, on the right side and on the wrong side alike.
- The number at the end of each line is the number of stitches it has when it is finished; chains and slip stitches that are not named there are not counted.
- Whip stitch: hold the two edges together and sew them over and over, the needle always going in from the same side, through one stitch of each edge at a time.
- Change yarn after every second row. The change always falls at the lower edge, which is the brim: work the last half double crochet of the row until 3 loops are on the hook, then yarn over with the other yarn and pull it through all 3. Do not cut the yarn not in use: hold it on the right side of the panel, the side away from you as the row ends, and carry it loosely up the lower edge on that side to where it is used again; the turned-up brim hides it. Yarn A is not used in the last 2 rows: when you change to yarn B for them, cut yarn A, leaving a tail of 6 in (15 cm).
- Man: for a head of 23 in (58 cm). The finished hat is about 20¾ in (53 cm) round and about 10 in (25 cm) deep with a brim of about 2 in (5 cm) turned up (about 12 in (30 cm) long before it is turned up).

For your own crochet, gifts and handmade pieces you sell. Do not resell or share this PDF.

Instructions

Chosen: Man, head 23 in (58 cm). The count in round brackets at the end of a line is what that line leaves. Tick the box when a row is done. In UK terms sc is double crochet and hdc is half treble.

Yarns in order of use: A, pine; B, ecru.

☐ **Foundation**	Ch 41.	
☐ **Row 1 (RS)**	Hdc in 3rd ch from hook and in each ch across	**(39 hdc)**
☐ **Row 2**	Ch 2, turn; sc in BLO of next 6 sts, hdc in BLO of next 33 sts	**(6 sc, 33 hdc)**
☐ **Row 3**	With B, ch 2, turn; hdc in BLO of next 33 sts, sc in BLO of next 6 sts	**(33 hdc, 6 sc)**
☐ **Row 4**	Ch 2, turn; sc in BLO of next 6 sts, hdc in BLO of next 33 sts	**(6 sc, 33 hdc)**
☐ **Row 5**	With A, ch 2, turn; hdc in BLO of next 33 sts, sc in BLO of next 6 sts	**(33 hdc, 6 sc)**
☐ **Rows 6 to 52**	Repeat rows 2 to 5 in order, over and over. The last row, row 52, is worked as row 4.	

A box for each row, 6 to 52: tick them off as you go. The heavy box is where you stop and measure.

6	7	8	9	**10**	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31	32	33	34
35	36	37	38	39	40	41	42	43	44	45	46	47	48	49	50	51	52											

> **Stop and measure when you have worked row 10.** After row 10, lay the panel flat without stretching it and measure it along a row: it should be about 12 in (30 cm) long. Then measure across the rows, in the part that is half double crochet and not at the single crochet end: the 10 rows, not stretched, should measure about 4 in (10 cm) from the outer side of row 1 to the outer side of row 10. This sets the size round: if they measure more, begin again with a smaller hook; if less, with a larger one. If the 10 rows measure right and the row is longer or shorter than it should be, keep the hook: the hat only comes out that much deeper or shallower.

☐ **End** Fasten off, leaving a tail of 40 in (102 cm) for the seam.

Assembly

1. Seam: fold the panel in half with the right side out, so that the last row lies against the beginning chain. The edge where the long tail hangs is the lower edge. With that tail whip stitch the first 6 stitches from the lower edge, one stitch of the last row to one chain: this part is turned up later, so its seam is sewn from the side that will be hidden. Then turn the panel so that the right side is in and whip stitch the rest in the same way, up to the top. Fasten off and turn the hat right side out.

2. Top: the top is the edge where the rows have their single crochet stitches. Cut a strand of yarn B 55 in (140 cm) long and thread it in the needle. Run it in and out through the edge all the way round, taking one stitch in the end of every second row. Pull it up tight so that the top closes, run it round once more through the same places, pull again, and fasten it firmly on the inside.

3. Brim: turn the lower edge up to the outside by about 2 in (5 cm).

Finishing

- Weave in every end on the inside of the hat, except an end that lies in the part that is turned up: weave that one in on the right side, which the turned-up brim hides.

In all: 52 rows; 2,028 stitches; 4 ends to weave in.

Found a mistake in this pattern? Tell us at flossfield.com, under Make a request.

For your own crochet, gifts and handmade pieces you sell. Do not resell or share this PDF.