Small upright piano and teapot

Sized for a 6 inch hoop (15 cm). The stitched design is about 3.3 × 4.4 in (8.4 × 11.2 cm).



Which color goes where: by number on page 2.

Stitch in this order

Filled parts from the back of the picture forward, then lines, loops and knots.

1. **Satin stitch**, 2 strands
   Frame rails, side posts, leaves, front legs, lid, rails and plinth, white keys, black keys, cheeks, cheek scrolls, pedals, feet, doily, and 13 more
2. **Trellis stitch**, 2 to 3 strands
   Lattice
3. **Chain stitch**, 4 strands
   Post chains
4. **Stem stitch**, 2 strands
   Post lines, vine
5. **Straight stitch**, strands by part on page 2
   Flower, leg rings
6. **Back stitch**, 1 strand
   Key lines
7. **Split stitch**, 1 to 2 strands
   Teapot ribs
8. **Lazy daisy stitch**, 3 strands
   Flower
9. **French knot**
   strands by part on page 2, two wraps
   Berries, flower heart, doily knots

Floss

- **1 DMC 3810 Dark Turquoise**
  Frame rails, side posts, cheeks, front legs and leaves
- **2 DMC 598 Light Turquoise**
  Lattice (lighter), steam and post chains
- **3 DMC 3808 Ultra Very Dark Turquoise**
  Lid, rails and plinth, note beam, post lines, note heads and vine and 2 more parts
- **4 DMC 349 Dark Coral**
  Teapot and teapot lid (middle), spout, handle, doily knots, berries and flower heart
- **5 DMC 783 Medium Topaz**
  Pedals, flower, feet, lid rim, teapot knob, leg rings, spout lip and cheek scrolls
- **6 DMC 3865 Winter White**
  White keys and doily
- **7 DMC 3799 Very Dark Pewter Gray**
  Black keys and key lines
- **8 DMC 498 Dark Red**
  Teapot and teapot lid (dark), teapot ribs and teapot foot
- **9 DMC 350 Medium Coral**
  Teapot and teapot lid (light)
- **10 DMC 352 Light Coral**
  Teapot shine

Three ways to transfer the pattern

1. **Fabric you can see through**
   Tape page 3 to a sunny window or lay it on a light box, tape the fabric over it and trace the lines with a sharp pencil or a water-soluble pen.
2. **Fabric you cannot see through**
   Lay dressmaker's carbon paper colored side down on the fabric with page 3 on top, tape the layers and trace the lines firmly with a ballpoint pen.
3. **Iron-on: the lines stay**
   Go over the lines of page 4, the mirrored page, with an iron-on transfer pen, lay it ink side down on the fabric and press with a dry iron, as the pen's packet says.

Pages 3 and 4 are the pattern at actual size. Print them at 100% with scaling turned off. Then put the fabric in the hoop: inner ring under, drawing up, tight as a drum.

For your own stitching, gifts and handmade pieces you sell. Do not resell or share this PDF or copies of it.

Small upright piano and teapot

6 inch hoop

How to read it

Floss is six strands. Cut 18 inches (45 cm), pull out the number given one at a time, and lay them together.

Inside a filled shape start with two or three tiny stitches, which the filling covers. Start a line with a small knot on the back. End each thread by running the needle under the backs of a few stitches.

Each small ring is one French knot. Each small loop is one lazy daisy: come up at its point.

A number on the picture is a color of the list of floss on page 1. The fine lines on the colors show which way the stitches lie.

Every stitch in pictures: flossfield.com/embroidery/stitches. The first time: flossfield.com/embroidery/guides/how-to-start.



1 DMC 3810 Dark Turquoise
2 DMC 598 Light Turquoise
3 DMC 3808 Ultra Very Dark Turquoise
4 DMC 349 Dark Coral
5 DMC 783 Medium Topaz
6 DMC 3865 Winter White
7 DMC 3799 Very Dark Pewter Gray
8 DMC 498 Dark Red
9 DMC 350 Medium Coral
10 DMC 352 Light Coral

How many strands

Straight stitch. 3 strands: leg rings; 2 strands: flower.
French knot. 2 strands: berries, flower heart; 1 strand: doily knots.

For your own stitching, gifts and handmade pieces you sell. Do not resell or share this PDF or copies of it.

Small upright piano and teapot

6 inch hoop

Print at 100% and check the square below with a ruler. Fold the fabric in four: the folds meet the four ticks of the ring.



1 in
25.4 mm

Check square: 1 inch (25.4 mm) on each side.
If it measures anything else, print again at 100% with scaling off.

For your own stitching, gifts and handmade pieces you sell. Do not resell or share this PDF or copies of it.

Small upright piano and teapot

6 inch hoop

Mirrored. Trace this page with an iron-on transfer pen or pencil, then press it ink side down on the fabric.



1 in
25.4 mm

Check square: 1 inch (25.4 mm) on each side.
If it measures anything else, print again at 100% with scaling off.

For your own stitching, gifts and handmade pieces you sell. Do not resell or share this PDF or copies of it.